

MidOhio.Net Dial-Up Access Settings Windows 95 / Windows 98

1. Double click on the "My Computer" icon.
2. Double click on the "Dial-Up Networking" icon. (If you do not see this icon, go to **Add Dial-Up Networking Component** at the end of these setup instructions)
3. If this is the first time you have opened "Dial-Up Networking," the "Make New Connection" wizard will automatically begin. If this is not the first time you have opened "Dial-Up Networking," double click on the "Make New Connection" icon.
4. Overtyping "My Connection" with "**MidOhio.Net**"
5. Click "Next."
6. Enter the "Area code" and "Telephone number" from the following table.

Your Location (by local phone prefix, not city)	Area Code*	Telephone Number
Ashville, Mount Sterling	614	3408743
London, Pataskala, Plain City	614	6756797
Delaware, Johnstown, Sunbury	740	3624636
Baltimore, Lancaster	740	4220121
Centerburg, <i>Franklin County</i>	740	5491300
Marysville, Richwood	937	3482230
North Lewisburg, West Mansfield	937	6426432

**Enter the area code only if it is required to make this call from your location.*

7. Click "Next."
8. Click "Finish."
9. Right click on the "MidOhio.Net" icon and select "Create Shortcut" from the command window. If a shortcut message opens, click "Yes."
10. Right click on the "MidOhio.Net" icon again and select "Properties" from the command window.
11. Select the "Server Types" tab.
12. Uncheck the box beside "**Log on to network.**"
13. Uncheck the boxes beside "**NetBEUI**" and "**IPX/SPX Compatible**". "**TCP/IP**" should be checked.
14. Click on the "TCP/IP Settings" button.
15. "**Server assigned IP address**" should be marked. Mark "**Specify name server addresses.**"
16. Enter the Primary DNS address **209.190.102.2** and the Secondary DNS address **209.190.102.9**
17. Click "OK" twice.
18. Double click on the "MidOhio.Net" icon and enter your username (*lowercase*) and password (*case sensitive*).
19. Click "Connect." (If you are unable to connect, continue with the setup instructions on page 2)

Configure Network:

1. Double click on the "Control Panel" icon.
2. Double click on the "Network" icon.
3. Under the "Configuration" tab, look for a "Dial-Up Adapter" component listed. If you see one "Dial-Up Adapter" component listed, continue to step 5.
4. If you do not see a "Dial-Up Adapter" component listed:
 - a. Click on "Add" button.
 - b. Double click on "Adapter" from the component.
 - c. Select Microsoft from the "Manufacturers" list.
 - d. Double click on "Dial-Up Adapter" from the "Network Adapters" list.
 - e. Click "OK" twice.
 - f. You will be asked to restart the computer. Click "Yes."
5. Under the "Configuration" tab, look for a "TCP/IP Dial-Up Adapter" component listed. If you see one "TCP/IP Dial-Up Adapter" component listed, continue to step 7.
6. If you do not see a "TCP/IP Dial-Up Adapter" component listed:
 - a. Click on the "Add" button.
 - b. Double click on "Protocol" from the component list.
 - c. Select Microsoft from the "Manufacturers" list.
 - d. Double click on "TCP/IP" from the "Network Protocols" list.
 - e. Click "OK" twice.
 - f. You will be asked to restart the computer. Click "Yes."
7. Under the "Configuration" tab, double click on the "TCP/IP Dial-Up Adapter" component. If a "TCP/IP Properties Information" message opens, click "OK."
8. Select the "IP Address" tab.
9. **"Obtain an IP address automatically"** should be marked.
10. Select the "DNS Configuration" tab.
11. **"Enable DNS"** should be marked.
12. In the "Host" field type *your username*.
13. In the "Domain" field type **midohio.net**
14. In the first "DNS Server Search Order" field (with three dots) type **209.190.102.2** and then click on the "Add" button. The set of numbers should appear in the field below. Back in the first field (with three dots), type **209.190.102.9** and click on the "Add" button again. The second set of numbers should also appear in the field below.

15. Select the "WINS Configuration" tab.
 16. **"Disable WINS Resolution"** should be marked.
 17. Click "OK" twice.
 18. You will be asked to restart the computer. Click "Yes." (Try to connect again)
-

Add Dial-Up Networking Component:

1. Double click on the "Control Panel" icon.
2. Double click on the "Add/Remove Programs" icon.
3. Select the "Windows Setup" tab.
4. Double click on the "Communications" component.
5. Check the box beside the "Dial-Up Networking" component.
6. Click "OK" twice.
7. You will be asked to restart the computer. Click "Yes." (Continue with the setup instructions on page 1)